

PicoCell Gateway V1.0 Graphical User Interface

WIRELESS & SENSING PRODUCTS

User Guide to the PicoCell Gateway V1.0 Graphical User Interface

Table of Contents

1	Pic	:oGV	V Tools Overview	.4		
	1.1	Pac	ket Forwarder	.4		
	1.2	HAI	_ Util Tx Continuous	.4		
	1.3	HAI	_ Util Tx Test	.4		
	1.4	Pac	ket Util Tx Test	.4		
	1.5	Pro	perties and Options Menus	.4		
2	Qu	ıick S	Start	.5		
	2.1	Pico	oGW User Interface	.5		
	2.1	1.1	Step 1: Startup	.5		
	2.1	1.2	Step 2: Open Packet Forwarder Utility	.5		
	2.1	1.3	Step 3: Open "Global Conf" Options	.6		
	2.1	1.4	Step 4: Global Configuration	.6		
	2.1	1.5	Step 5: Open Options	.7		
	2.1	1.6	Step 6: Options	.7		
	2.1		Step 7: Start the Packet Forwarder			
	2.2	Inte	gration into Semtech's Network Server	.9		
	2.2	2.1	Step 1: Create an Account	.9		
	2.2	2.2	Step 2: Register the Gateway	.9		
	2.2	2.3	Step 3: Add the Gateway	.9		
	2.2	2.4	Step 4: Enter Gateway Data	10		
	2.2	2.5	Step 5: Verification	10		
3	3 Packet Forwarder					
	3.1		ket Forwarder Controls			
	3.2	Filtering Options				
	3.3		ered Results			
	3.4		eway Statistics			
	3.5		sole Output: Log all Received Packets			
4			il Tx Continuous			
5		AL Util Tx Test				
6 7			Util Tx Testties: Options Menus			
,	7.1					
	7.1		Cloud Network			
				_		

/.1.2	2 Gateway Properties	16
7.1.3	SX1301 Properties	16
7.2 O	options	17
8 Pico	Cell Gateway Firmware Update	18
8.1.1	Step 1: Set the PicoCell Gateway in DFU Mode	18
8.1.2	2 Step 2: Open Dfuse Software	18
8.1.3	S Step 3: Flash the Gateway	19
9 Revis	sion History	20
	·	
List	of Figures	
Figure 1:	PicoGW Main Menu	4
Figure 2:	Quick Start Step 1	5
Figure 3:	Quick Start Step 2	5
Figure 4:	Quick Start Step 3	6
Figure 5:	Quick Start Step 4	6
Figure 6:	Quick Start Step 5	7
•	Quick Start Step 6	
Figure 8:	Quick Start Step 7	8
•	Quick Start Integration Step 2	
_	e: Quick Start Integration Step 3	
•	: Quick Start Integration Step 4	
_	2: Quick Start Integration Step 5	
_	: Packet Forwarder Main Menu	
•	l: Packet Forwarder Controls	
•	i: Filtering Options	
	s: Filtered Results	
•	': Gateway Statistics	
_	3: Console Output	
	9: HAL Util Tx Continuous	
•): HAL Util Tx Test	
•	: Packet Util Tx Test	
_	2: Properties	
	3: Options	
_	l: Gateway Upgrade Step 1	
_	i: Gateway Upgrade Step 2 i: Gateway Upgrade Step 3	
i igule 20	o. Jaicway Opyraue Step S	19

1 PicoGW Tools Overview

PicoGW Tools is a software set allowing easy command & control of Semtech's PicoCell Gateway.




Figure 1: PicoGW Main Menu

1.1 Packet Forwarder

Real-time display of received packets, also able forward them to a network server. This function allows packet filtering against any LoRa® parameter.

1.2 HAL Util Tx Continuous

Continuous sending of a LoRa® preamble or FSK sync word.

1.3 HAL Util Tx Test

Send packets at HAL level.

1.4 Packet Util Tx Test

Send a packet at packet forwarder level. This can be used to simulate a downlink.

1.5 Properties and Options Menus


Customize the packet forwarder behavior.

2 Quick Start

This section shows the main steps to have a functional packet forwarder connected to any network server compatible with Semtech's packet forwarder. This section will use Semtech's network server.

2.1 PicoGW User Interface

2.1.1 Step 1: Startup



2.1.2 Step 2: Open Packet Forwarder Utility





Figure 3: Quick Start Step 2

2.1.3 Step 3: Open "Global Conf" Options



Figure 4: Quick Start Step 3

2.1.4 Step 4: Global Configuration



2.1.5 Step 5: Open Options




Figure 6: Quick Start Step 5

2.1.6 Step 6: Options




Figure 7: Quick Start Step 6

2.1.7 Step 7: Start the Packet Forwarder




Figure 8: Quick Start Step 7

The packet forwarder is now sending all the received packets to the network server.

2.2 Integration into Semtech's Network Server

2.2.1 Step 1: Create an Account

Create an account according to your localization:

- https://eu.iot.semtech.cloud
- https://na.iot.semtech.cloud
- https://cn.iot.semtech.cloud
- https://apac.iot.semtech.cloud

2.2.2 Step 2: Register the Gateway




Figure 9: Quick Start Integration Step 2

2.2.3 Step 3: Add the Gateway



Figure 10: Quick Start Integration Step 3

2.2.4 Step 4: Enter Gateway Data




Figure 11: Quick Start Integration Step 4

2.2.5 Step 5: Verification




Figure 12: Quick Start Integration Step 5

You should now have a fully functional gateway redirecting packets to the network server.

3 Packet Forwarder

This is real-time display of received packets. You can forward them to a network server. This function allows packet filtering against any LoRa® parameter.




Figure 13: Packet Forwarder Main Menu

- 1. Packet Forwarder Controls
- 2. Filtering Options
- 3. Filtered Results
- 4. Gateway Statistics
- 5. Console Output Log all received packets

3.1 Packet Forwarder Controls



Figure 14: Packet Forwarder Controls

Controls can be used to start and stop the packet forwarder.

The Save Received Packets button saves all the received packets in a CSV file.

Use the *Open Log Folder* menu to open them.

Close will stop the packet forwarder and close the UI.

3.2 Filtering Options




Figure 15: Filtering Options

Filters can be applied on received packets in order to help data analysis.

3.3 Filtered Results




Figure 16: Filtered Results

Results matching the filter are displayed here. Start and stop statistics (Received packets, PER).

3.4 Gateway Statistics




Figure 17: Gateway Statistics

Statistics sent by the gateway are displayed here.

3.5 Console Output: Log all Received Packets



Figure 18: Console Output

All received packets are displayed in this frame without any filtering.

4 HAL Util Tx Continuous

Send continuously a LoRa® preamble or a FSK Sync Word.

All radio parameters can be selected and the packet type can be changed with the "modulation" option.




Figure 19: HAL Util Tx Continuous

5 HAL Util Tx Test

Send packets at HAL level, i.e. complete LoRa® or FSK packets.

Each parameter can be set to match the requested configuration. The packet type can be changed with the "modulation" option.




Figure 20: HAL Util Tx Test

6 Packet Util Tx Test

Inject a packet at a packet forwarder level. This can be used to simulate a downlink.




Figure 21: Packet Util Tx Test

7 Properties: Options Menus

7.1 Global Conf

This menu opens the configuration window.




Figure 22: Properties

7.1.1 Cloud Network

Allow packet forwarding to a public network if "Use a cloud network" box is checked.

- Use a cloud network: send data to a server defined in the "options" menu, in addition to the server defined in "server address"
- Server Address: enter the network server address
- Port: enter the port number of the network server

7.1.2 Gateway Properties

All gateway parameters can be set:

- ID: Gateway unique identifier (EUI-64). You can use the PicoCell Gateway's embedded microcontroller ID by using the button "get gateway unique ID" or set a custom ID by checking "use custom gateway ID" and entering an 8-byte ID.
- Keep alive interval: send a "keep alive" frame if required every X seconds
- Stat interval: send statistics every given time in seconds
- Push time-out: time-out in milliseconds
- Forward crc valid/error/disabled: allow forwarding packet according to their CRC status

7.1.3 SX1301 Properties

All radio properties can be changed. A set of predefined values can be applied with the button "Select configuration to restore". This is also useful to select another region.

7.2 Options




Figure 23: Options

The CSV delimiter and display parameters can be customized.

The packet forwarder can be displayed in any mode by checking the corresponding box.

"Show conf selector at starting" allows displaying the regional parameter windows at startup.

Use the button "Start in DFU mode" to update the PicoCell Gateway as in section 8.

8 PicoCell Gateway Firmware Update

The PicoCell Gateway can be updated with the "Dfuse" utility installed with the PicoCell GUI.

8.1.1 Step 1: Set the PicoCell Gateway in DFU Mode




Figure 24: Gateway Upgrade Step 1

The gateway must be set in DFU (Device Firmware Upgrade) mode in order to be updated.

8.1.2 Step 2: Open Dfuse Software




Figure 25: Gateway Upgrade Step 2

8.1.3 Step 3: Flash the Gateway




Figure 26: Gateway Upgrade Step 3

Note:

The firmware can be found in the directory <code>%appdata%\Semtech\PicoGW_UI\DFU</code>.

9 Revision History

Version	Date	Modifications
1.0	August 2017	First Release
1.1	March 2017	Update with details of Semtech's network server



Important Notice

Information relating to this product and the application or design described herein is believed to be reliable, however such information is provided as a guide only and Semtech assumes no liability for any errors in this document, or for the application or design described herein. Semtech reserves the right to make changes to the product or this document at any time without notice. Buyers should obtain the latest relevant information before placing orders and should verify that such information is current and complete. Semtech warrants performance of its products to the specifications applicable at the time of sale, and all sales are made in accordance with Semtech's standard terms and conditions of sale.

SEMTECH PRODUCTS ARE NOT DESIGNED, INTENDED, AUTHORIZED OR WARRANTED TO BE SUITABLE FOR USE IN LIFE-SUPPORT APPLICATIONS, DEVICES OR SYSTEMS, OR IN NUCLEAR APPLICATIONS IN WHICH THE FAILURE COULD BE REASONABLY EXPECTED TO RESULT IN PERSONAL INJURY, LOSS OF LIFE OR SEVERE PROPERTY OR ENVIRONMENTAL DAMAGE. INCLUSION OF SEMTECH PRODUCTS IN SUCH APPLICATIONS IS UNDERSTOOD TO BE UNDERTAKEN SOLELY AT THE CUSTOMER'S OWN RISK. Should a customer purchase or use Semtech products for any such unauthorized application, the customer shall indemnify and hold Semtech and its officers, employees, subsidiaries, affiliates, and distributors harmless against all claims, costs damages and attorney fees which could arise.

The Semtech name and logo are registered trademarks of the Semtech Corporation. All other trademarks and trade names mentioned may be marks and names of Semtech or their respective companies. Semtech reserves the right to make changes to, or discontinue any products described in this document without further notice. Semtech makes no warranty, representation or guarantee, express or implied, regarding the suitability of its products for any particular purpose. All rights reserved.

© Semtech 2018

Contact Information

Semtech Corporation
Wireless & Sensing Products
200 Flynn Road, Camarillo, CA 93012
E-mail: sales@semtech.com
Phone: (805) 498-2111, Fax: (805) 498-3804

www.semtech.com